

TagPro™

Next Generation Labels for Cables

DATA

Using the Online Label Generator




Information

Need some help?

Clicking “Need some help?” will present a “How To” PDF to the user.

CSV Import



Clicking the Import file button will present the user with a file selection modal.



The user can select their desired page size, A4 or US Letter.

Clicking the Choose File button allows the user to import a sequence via a .CSV file. Each row of the CSV file will be used to create a single tag.

The CSV is not limited with regard to the number of columns that may be used. The columns are added together to create a label, and the first 56 characters will be used. If the columns contain more text than that, it will be discarded.

Please note that if you are using an iOS device, then the CSV Import will only work on versions above iOS 9.

Creating A Sequence

Font colour

Clicking the Font Colour button will present a Colour Picker to the User, which can be used to select the sequence color.

How many tags do you need?

250

The number of tags needed should be entered in the corresponding field.

Each field will accept up to 20 characters but the maximum total number of characters across the 3 fields is 56.

Number 1 asdasdsas	Number 2 zcxccccxc	Number 3 bbvxzcbbbbccc
<input type="checkbox"/> Auto Increment	<input type="checkbox"/> Auto Increment	<input type="checkbox"/> Auto Increment

When the Auto Increment box is ticked the number in the corresponding field will be incremented when printing, e.g. if AB1 is entered in the first field and the Auto Increment box is ticked, the sequence will print AB1, AB2, AB3 etc.

A warning will be displayed to the User if using the Auto Increment feature would lead to the maximum number of characters being exceeded.

Font colour	How many tags do you need? 500	
Number 1 a b c a b c a b c a b c a b c a b	Number 2 a b c a b c a b c a b c a b c a	Number 3 a b c a b c a b c a b c a b c a b c 1
<input type="checkbox"/> Auto Increment	<input type="checkbox"/> Auto Increment	<input checked="" type="checkbox"/> Auto Increment

Auto incrementing the selected component would make the sequence exceed the permitted maximum number of characters.

Note:

- The Auto Increment feature can not be applied if the corresponding field does not contain a number.
- Only one field of the three can be set to Auto Increment.

Preview

Test111111111 Test111111111
Test111111111 Test111111111

A Preview of the first tag of the sequence to be generated is displayed in the Preview box.

Page Size Selection

A4 Paper

US Letter Paper

The user can select between the 2 supported page sizes:

A4 paper can contain a maximum of 112 tags per page.

US Letter paper can contain a maximum of 98 tags per page.

Generate PDF

Clicking the Generate PDF button will create a PDF containing all of the generated sequences.

Managing Sequences

Add Sequence +

Clicking the Add Sequence button adds a sequence below the previous.

Delete Sequence 


Clicking the Delete Sequence button deletes the corresponding Sequence.

Total amount of tags: **336**

You will need 3 sheets of [TagPro](#) Data paper to complete this job

The total amount of tags to be printed and the number of sheets of TagPro Data paper required is displayed.

User Feedback



A screenshot of a feedback form with the following fields: Name (input field), Email (input field), Message (text area), and a green Send button at the bottom.

The user may enter their name and email address and send any feedback via the Customer Feedback form.

Printing

Please note that when printing the PDF, the user must ensure that the printer settings are configured not to scale the PDF. A4 or US Letter must be set accordingly and if scaling is automatically set, a scaling percentage of 100% must be set otherwise the printed tags may not fit within the TagPro Data paper tags.